wiki.skylark.tv - https://wiki.skylark.tv/

MAM Web Access Server

The information is relevant for Skylark SLNeo 2.6.37 software and higher.

Skylark MAM Web Access Server provides the cross-platform client web-app that allows managing playlists from the browser, exchanging messages and working with materials in the server MAM/Playout media database. The service is useful in case of working with a system other than Windows, not having a permanent workplace or connecting to the Skylark infrastructure remotely through the Internet.

1/9

List of Supported Functions

- Viewing content of the server MAM database.
- Frame-by-frame viewing clips in the WebProxy quality.
- Viewing and editing metadata and key frames.
- Archiving and restoring.
- Import/export of materials.
- Managing playlists of broadcasting servers.
- Managing recording services.
- Exchanging messages via the Messenger service.

Launch

Launch of the server part is implemented by clicking the MAM Web Access Server icon. Note that correct work of the application requires full access to the folder "C:\Program Files (x86)\SL NEO Media Platform". There are three permission options:

- Grant full access to the folder for the current user. The permission is permanent.
- Onetime launch of the program as an administrator, valid until the software is reloaded. Right-



- click the MAM Web Access Server icon \rightarrow Launch as an administrator.
- Permanent launch of the program as an administrator. Right-click the MAM Web Access Server icon→Properties→Compatibility→Launch this program as an administrator.

As MAM Web Access Server interacts with the media database, program channels, and recorders, it is required to launch SL NEO Media Server with configured services beforehand. MAM Web Access Server can operate at the same server as SL NEO Media Server, or implement connection to it through the local network.

Note that MAM Web Access Server may actively use processor resources for recoding operations, and the disk subsystem for upload/download operations. In case of a big number of clients, it is recommended to launch the app at a separate server or assign a separate disk for storing temporary files.

Starting from version 2.5.1, it is possible to launch several MAM Web Access at one server.

The command line format for launching several apps: C:\Program Files (x86)\SL NEO Media Platform\mamproject.exe N, where N is the sequence number of the launched copy.

Example:

- mamproject.exe 1
- mamproject.exe 2
- mamproject.exe 3

Calculating the port number to connect the created MAM Web Access copy to the web-interface is implemented by the formula: 7701+2*(N-1), where N is the sequence number of the launched copy.



Launched MAM Web Access Server places its icon near the clock.

Presetting

The option of viewing materials requires configuring WebProxy generation in the MP4 format in MAM database settings.

Admin Interface (Control Panel)

All settings implemented in the control panel are saved to the file: "C:\Program Files (x86)\SL NEO Media Platform\run\mam_config.xml".



Login to the Administrator Control Panel is implemented by clicking the mamserver service icon, or

through the browser by the address: IP_ADDRESS:7701/admin. Before version 2.4.129, access to the interface had been implemented by the 7801 port.

😨 mamproject			_ 🗆 ×		
	-6	Licensed Unique Sessions:	3		
Configure		Active Unique Sessions:	1		
		Channels:	0		
LI	cense	Total Connections:	1		
Syst	em Log	Status:	Running Stop		
Current	Connections				
Parameter	Description		1		
Server	Opens the window with	basic WebAccess server se	ttings		
Profile	Configure encoding pro	files of media materials.			
Workspaces	Configure user workspaces. The workspace includes preliminarily grouped connections to media databases, program channels, recorders and messenger services that may be associated with user accounts.				
Users	User control. The dialog selected in WebAccess	User control. The dialog is available, when the local authentification type is selected in WebAccess; WebAccess→Server→Authentication Type = MAM			
License	License information.	License information.			
Change Admin Passwords	Changing the admin password used to log in to the WebAccess control panel.				
System Log	Displaying the log of cu	irrent user activity in the rea	al-time mode.		
Current Connections	🕆 Fix Me!				
Licensed Unique Sessions	🔭 Fix Me!				
Active Unique Sessions	The number of active u	nique connections to the ap	plication web-interface.		
Channels	🔧 Fix Me!				
Total Connections	🕆 Fix Me!				
Status	The app web-interface status. Running - launched and available to users, Stopped - the app is stopped and unavailable, users get the "Server is under maintenance" message				
Start/Stop	The button to launch ar	nd stop the portal web-serve	er.		

Server Menu (Admin Config)

Admin Config

Server workpath:	Z:\===SLNEO\WebAccessWorkpati		
Max Transcode Threads:	1		
Max Zip Threads:	1		
Default Profile:	WP1	J	
Metadata Schema Address:			
Metadata Schema Service ID:	1		
Authentication Type:	Storage	I	

Authentication Server

Address:	127.0.0.1	
Service ID:	1	•
	-	•

Ok	Cancel
----	--------

Parameter	Description
Server workpath	A path to the folder at the local disk used for storing temporary data.
Max Transcode Threads	The maximum number of transcoding streams used for up/unloading files by users.
Max Zip Threads	The maximum number of archiving streams. Archiving is used in case when more than one file is selected for downloading.
Default Profile	
Metadata Schema Address	Address of the server with the media database that contains the configured metadata schema (as a rule, it's the server MAM database).
Metadata Schema Service ID	The sequence number of the utilized media database service.
Authentication Type	 Select the user authorization mechanism for the login to the client web-interface: Storage - Activates authorization through the media database service. Users are added in settings of the remote server media database, on the tab: Neovid→Administrator Control Panel→Status→Storage_N→Manage Users. In this authorization mode, Default Workspace is used for connecting users. MAM - activates the built-in authorization mechanism. Users are added in the WebAccess→Users menu. In this authorization mode, connecting users is implemented through the individual Workspace defined in the server settinge.

Parameter	Description			
	Information on the remote authentication server. The authentication server is the one with the configured media database that has users specified.			
Authentication Server	Address — the remote server IP-address. If the media database is located at the local server, enter the 127.0.0.1 IP address.			
	Service ID - the sequence number of the media database service. The item is available in case if Authentication Type=Storage			

Profiles Menu

Workspaces Menu

Workspaces

efault Workspace:	DemoWorkspace	•	
DemoWorkspace		~	Add
o chorron opuce			Edit
			Delete
		~	Rename
Ok		Cancel	

Parameter	Description
Default Workspace	Select the default workspace to be utilized by users upon selecting the Authentication Type=Storage authorization mode.
Add	Adding a workspace.
Edit	Editing the workspace.
Delete	Removing the selected workspace.
Rename	Renaming the selected workspace.

Edit Workspace

ame: Dem	oWorkspace	2				
Storages	Castlists	Reclists	Messenge	rs		
Name	×.	Address	₩ _A	Service		Add
MediaDB		127.0.0.1		1		Edit
						Delete
<					>	
	Ok			Cance		

Paramete	er Descript	ion					
Name	Workspac	e nam	e.				
	The list of Add Stor	The list of media databases available in the workspace. Add Storage					
Storages	Name: Address:	Media2					
	Service:	1	÷				
	Ok	Ok Cancel					
	Upon cont address, s	figurin service	g the conne sequence r	ction, specify: the media database displayed name, server IP number at the remote server (starts with 1).			
	The list of Add Castlist	progr	am channels	available for management in the workspace.			
	Name:	CAST2					
	Host:						
Castlist	Num:	1	:				
	⊠ M⊡ 2□	3 4 9	5 6 7 8 9				
	Ok	Ok Cancel					
	Upon con sequence of layers a	figurin numb availat	g the conne er of the pro lle for mana	tion, specify: the playlist displayed name, server IP address, gram channel at the remote server (starts with 1), numbers gement.			

Parameter	Description						
	The list of recording services available for management in the workspace. Edit Reclist						
Rectlists	Name: REC1 Host: 127.0.0.1 Num: 1 Ok Cancel Upon configuring the connection, specify: the rec-list displayed name, server IP address, sequence number of the recording service at the remote server (starts with 1).						
	The list of messenger servers used in the workspace. Add Messenger Name: Mess1						
Messengers	Address:						
	sequence number of the messenger service at the remote server (starts with 1).						

Users Menu

User management is available if the built-in authorization mechanism is active: WebAccess→Server→Authentication Type=MAM.

User Profiles

"demo"	^	Add
		Edit
	~	Delete
Ok	Cancel	

The main window for user management. It displays the list of users and allows adding/editing user accounts.

Add User

General	Storages	Broadcast	Lists	Record Lists
Messenger	5			
User:			demo	
Password:				
Workspace	s:			
Demo W	orkspace	^		Add
		~		Delete
	Ok			Cancel

The General tab allows specifying the login/ password and associating the workspace with the user account.

Parameter	Description			
User	Specify or edit the login.			
Password	Specify and edit the password. If the password wasn't edited, the field would display the Unchanged value.			
Password	Define the list of workspaces to be associated with the user account. Information for authorization in the connected resources defined by the selected workspaces, are specified at the corresponding tabs: Storages, Broadcast Lists, Record Lists и Messengers. Add User Add User Image: Define the list image: Define the list image: Define the list image: Define the list image: Define the corresponding tabs: Storages, Broadcast Lists, Record Lists и Messengers. Add User Add User Image: Define the list image: Define the list image: Define the list image: Define the corresponding tabs: Storages, Broadcast Lists, Record Lists u Add User Image: Define the list image: Define the			
	lser - user name used for connecting to the media database or messenger services			
	User - user name used for connecting to the media database or messenger services. The value depends on the remote service settings.			
	Password - user password used for connecting.			

License Menu

Displaying information on the parameters of the installed license key. The "Enter License..." button opens a dialogue for entering the license key.

"Change Admin Password" Menu

The menu allows changing the admin password used to log in to the WebAccess control panel.

System Log Menu



Current Connections Menu

Displays the list of active connections with IP addresses.

Licensing

Skylark MAM Web Access Server uses one connection to the MAM database (included to the MAM server license). The number of users able to connect Web Access simultaneously via the web-interface is set in the Web Access server license, in the Licensed Unique Sessions field.

From: https://wiki.skylark.tv/ - wiki.skylark.tv

Permanent link: https://wiki.skylark.tv/manual/mamproject

Last update: 2020/07/07 08:17

